

LINE ID	INDICATOR SETTINGS	DEFAULTS	NOTES
1.0	Group 1Account/Start Day	Group 1Account/Start Day	
1.1	Account	SIM101	Requires setting to be APPLIED for each monitored account
1.2	Day Start Hour (0-23), Computer	17	Only whole hours allowed based on your computer clock
2.0	Group 2: Daily Settings	Group 2: Daily Settings	
2.1	Daily Drawdown WARNING (\$)	\$650	"9999" to remove Warning Circuit Breaker
2.2	Daily Drawdown HALT (\$)	\$800	In order to maintain this spread from the current Daily PnL Peak, enable Daily Trailing Stop.
2.3	Daily Trailing Stop	TRUE	If enabled, maintains spread from current price to Daily Drawdown HALT (\$)
2.4	Daily Max Trade Updates	1000	Read Caution Note! Each hit on account classifies as a "Trade".
2.5	Daily Max Loss Updates	1000	Read Caution Note! Each hit on account classifies as a "Trade".
3.0	Group 3: Daily Level 1	Group 3: Daily Level 1	
3.1	Daily Goal 1	\$800	
3.1	Daily Dynamic Drawdown WARNING (%)	20%	"999" to remove Warning Circuit Breaker or any number larger than HALT value.
3.3	Daily Dynamic Drawdown HALT (%)	90%	0% will stop trading; 100% will allow Goal 1 to be given all back.
4.0	Group 4: Daily Level 2	Group 4: Daily Level 2	Current Chart Input
4.1	Daily Goal 2	\$1,600	
4.2	Daily Dynamic Drawdown WARNING (%)	33%	"9999" to remove Warning Circuit Breaker
4.3	Daily Dynamic Drawdown HALT (%)	50%	0% will stop trading; 100% will allow Goal 1 to be given all back.
5.0	Group 5: Weekly Settings	Group 5: Weekly Settings	
5.1	Weekly Drawdown WARNING (\$)	\$2,000	"9999" to remove Warning Circuit Breaker
5.2	Weekly Drawdown HALT (\$)	\$2,100	0% will stop trading; 100% will allow Goal 1 to be given all back.
6.0	Group 6: Weekly Level 1	Group 6: Weekly Level 1	
6.1	Weekly Goal 1	\$2,000	
6.2	Weekly Dynamic Drawdown WARNING (%)	33%	"9999" to remove Warning Circuit Breaker
6.3	Weekly Dynamic Drawdown HALT (%)	50%	0% will stop trading; 100% will allow Goal 1 to be given all back.
7.0	Group 7: Weekly Level 2	Group 7: Weekly Level 2	
7.1	Weekly Goal 2	\$2,500	
7.2	Weekly Dynamic Drawdown WARNING (%)	25%	"9999" to remove Warning Circuit Breaker
7.3	Weekly Dynamic Drawdown HALT (%)	50%	0% will stop trading; 100% will allow Goal 1 to be given all back.
8.0	Group 8: Options	Group 8: Options	
8.1	Include Unrealized Orders	FALSE	Calculates Intra Trade
8.2	Close Existing Open Positions	TRUE	If enabled and "Include Unrealized Orders" is FALSE, if exiting an order breached your rule the Discipline Manager will close open positions; if FALSE open positions will remain. Once the open positions is realized and no longer breaching rule, you can continue to trade.
9.0	Group 9: Daily Stats	Group 9: Daily Stats	

LINE ID	INDICATOR SETTINGS	DEFAULTS	NOTES
9.1	Daily PnL	TBD	"To Be Determined" requiring first order to calculate.
9.2	Daily PnL Peak	TBD	"To Be Determined" requiring first order to calculate.
9.14	Daily Trailing Balance	TBD	"To Be Determined" requiring first order to calculate.
10.0	Group 10: Weekly Stats	Group 10: Weekly Stats	
10.1	Weekly PnL (Sun-Sat)	TBD	"To Be Determined" requiring first order to calculate.
10.2	Weekly PnL Peak	TBD	"To Be Determined" requiring first order to calculate.
11.0	Group 11: Goal Stats	Group 11: Goal Stats	
11.1	Daily Goal Hit 1	TBD	"To Be Determined" requiring first order to calculate.
11.2	Daily Goal Hit 2	TBD	"To Be Determined" requiring first order to calculate.
11.14	Weekly Goal Hit 1	TBD	"To Be Determined" requiring first order to calculate.
11.14	Weekly Goal Hit 2	TBD	"To Be Determined" requiring first order to calculate.
12.0	Group 12: Trade Stats	Group 12: Trade Stats	
12.99	Trade Count	TBD	"To Be Determined" requiring first order to calculate.
12.99	Trade loss Count	TBD	"To Be Determined" requiring first order to calculate.
13.0	Group 13: Alert Logging	Group 13: Alert Logging	
13.1	Log Alert	TRUE	
13.2	Play Alert Sound	TRUE	
14.0	Group 14: Set as Default	v1.1 Aug 01, 2021 (NT8)	Saves default values
15.0	Group 15: Export	EXPORT v2.2 Aug 30, 2021 (NT8)	Exports .txt file to local desktop